



Revision History



<u>Revision</u>	<u>Revision Description</u>	<u>Date</u>
2.0	Revised Release, Version 3.01	9 April 2002
2.1	Update, Version 3.01	11 July 2002
Review only	Update, Version 3.01	19 Sep 2002

Revision 2.2: TC-AIMS II – IBS Interface Agreement Changes

1. Page 11, Table A-4, Unit Movement Data Detail Delete “DD” Record.

CURRENT:

Table A-4, Unit Movement Data Detail Delete “DD” Record

DESCRIPTION	POSITIONS	WIDTH	TYPE/ CLASS	REMARKS															
RECORD TYPE	1	1	A	Always “D” for delete	M														
TRANSACTION CODE	2	1	A	Always “D” delete	M														
TCN	3 - 19	17	A/N	<table><tr><th>Pos</th><th>Meaning from DTR 4500.9-R</th></tr><tr><td>1</td><td>Service code (A-Army, F-Air Force, M-Marine Corps, NNavy, and Z-Coast Guard)</td></tr><tr><td>2-8</td><td>Army activities will enter a Unit Identification Code (UIC) beginning with TCN position 2 and putting a \$ (dollar) special character in position 8. All other Services will enter a Unit Line Number (ULN) beginning with TCN position 2 and filling any unused positions with a \$ (dollar) special character.</td></tr><tr><td>9-10</td><td>Service use, except for code “CH” which is reserved to identify small units (10 tons of equipment or less) moving by air. Requires data entry, do not leave blank. Use zeros if no data available.</td></tr><tr><td>11-14</td><td>Shipment number, increment number, or serial number.</td></tr><tr><td>15</td><td>Unit cargo TCN indicator. (Enter a zero here).</td></tr><tr><td>16-17</td><td>Split/partial shipment or complete shipment unit indicator.</td></tr></table>	Pos	Meaning from DTR 4500.9-R	1	Service code (A-Army, F-Air Force, M-Marine Corps, NNavy, and Z-Coast Guard)	2-8	Army activities will enter a Unit Identification Code (UIC) beginning with TCN position 2 and putting a \$ (dollar) special character in position 8. All other Services will enter a Unit Line Number (ULN) beginning with TCN position 2 and filling any unused positions with a \$ (dollar) special character.	9-10	Service use, except for code “CH” which is reserved to identify small units (10 tons of equipment or less) moving by air. Requires data entry, do not leave blank. Use zeros if no data available.	11-14	Shipment number, increment number, or serial number.	15	Unit cargo TCN indicator. (Enter a zero here).	16-17	Split/partial shipment or complete shipment unit indicator.	M
Pos	Meaning from DTR 4500.9-R																		
1	Service code (A-Army, F-Air Force, M-Marine Corps, NNavy, and Z-Coast Guard)																		
2-8	Army activities will enter a Unit Identification Code (UIC) beginning with TCN position 2 and putting a \$ (dollar) special character in position 8. All other Services will enter a Unit Line Number (ULN) beginning with TCN position 2 and filling any unused positions with a \$ (dollar) special character.																		
9-10	Service use, except for code “CH” which is reserved to identify small units (10 tons of equipment or less) moving by air. Requires data entry, do not leave blank. Use zeros if no data available.																		
11-14	Shipment number, increment number, or serial number.																		
15	Unit cargo TCN indicator. (Enter a zero here).																		
16-17	Split/partial shipment or complete shipment unit indicator.																		
LOAD NUMBER	20	1	A/N	Mandatory for ARMY cargo only: If the 10th position of the TCN is an “E”, then this field will be filled with the appropriate letter of the Load to be deleted using one of the following: “A to D”, “F to N”, or “P to Z”. If the 10th position of the TCN is a “G”, then this field will be filled with the appropriate letter of the Load to be deleted using one of the following: “A to D”, “F”, “H to N”, or “P to Z”. Blank for all other services data as determined by the first character of the TCN.	O														
M = Mandatory field field O = Optional field C = Conditional A = Alpha N = Numeric																			

REVISED the positions following the VEHICLE LOAD FLAG OR LOAD NUMBER (revised to positions 20 –21, length 2).

ADDED the PARENT TCN to the end of the record.

(Replace Table):

Table A-3, Unit Movement Data Detail Add “DA” or Change “DC” Record

DESCRIPTION	POSITIONS	WIDTH	TYPE/ CLASS	REMARKS	
RECORD TYPE	1	1	A	Always “D” for delete	M
TRANSACTION CODE	2	1	A	Always “D” delete	M
TCN	3 - 19	17	A/N		M
				Pos	Meaning from DTR 4500.9-R
				1	Service code (A-Army, F-Air Force, M-Marine Corps, NNavy, and Z-Coast Guard)
				2-8	Army activities will enter a Unit Identification Code (UIC) beginning with TCN position 2 and putting a \$ (dollar) special character in position 8. All other Services will enter a Unit Line Number (ULN) beginning with TCN position 2 and filling any unused positions with a \$ (dollar) special character.
				9-10	Service use, except for code “CH” which is reserved to identify small units (10 tons of equipment or less) moving by air. Requires data entry, do not leave blank. Use zeros if no data available.
				11-14	Shipment number, increment number, or serial number.
				15	Unit cargo TCN indicator. (Enter a zero here).
				16-17	Split/partial shipment or complete shipment unit indicator.
LOAD NUMBER	20-21	2	A/N	Mandatory for ARMY cargo only: If the 10th position of the TCN is an “E”, then this field will be filled with the appropriate letter of the Load to be deleted using one of the following: “A to D”, “F to N”, or “P to Z”. If the 10th position of the TCN is a “G”, then this field will be filled with the appropriate letter of the Load to be deleted using one of the following: “A to D”, “F”, “H to N”, or “P to Z”. Blank for all other services data as determined by the first character of the TCN.	O
PARENT TCN	22-38	17	A/N	TCN of the associated Prime Mover for child cargo. Blank for prime movers.	
M = Mandatory field C = Conditional O = Optional field A = Alpha N = Numeric					

<u>Approval Signatures for Revision 2.2 Update, Version 3.01</u>		
	<u>Date</u>	<u>Signature</u>
GARY L. WINKLER PM, TIS	_____	_____
JACQUELINE HENDERSON Chief, IBS Branch	_____	_____